

MEDAQLib

Quick reference

Micro-Epsilon Data Acquisition Library



Content

1. Introduction
2. Advantages against Low-Level Programming
3. Supported programming languages, hardware interfaces and sensors
4. System requirements
5. Internal structure of the MEDAQLib
6. Basic structure of an application
7. Example program

1. Introduction

- **Why necessary: Wide range of sensors types**
 - Many different sensors with completely different protocols
 - Diverse interface possibilities, fractional multiple per sensor
 - Complex emdedding of drivers (e.g. Windows sockets, USB)
- **What is MEDAQLib?**
 - Free Software and Driver Library for software developer
 - Applicable for all programming languages, which can use DLLs
 - Receiving, buffering and processing measured values
 - Setup and controlling of sensors via a unified programming interface
- **What is MEDAQLib not?**
 - Ready to use Measurement Software with a user interface

2. Advantages against Low-Level Programming

- Data transfer protocol and converting formulas don't need to be learned
 - Sensor commands don't need to be generated manually, automatic parameter range check
 - All commands of each sensor will be build equally
 - Available examples for many programming languages and for many sensors
- Fast success at implementation
- High reuseability of code when changing interface or sensor

3. Supported Programming languages, hardware interfaces and sensors



Software	Programming language		C C++	VB 6.0 VBA (e.g. Excel)	.net (VB, C#)	Delphi	MatLab LabView ...	ICONNECT	...			
	Driver	MEDAQLib (DLL interface)										
Computer		RS232 driver (Windows)			IF2004_USB driver	WinUSB	IF2004 driver	IF2008 driver	TCP/IP client/server, UDP (Windows socket)			
		native RS232 interface	USB interface					IF2004 card	IF2008 card	Ethernet interface		
			RS232 / USB conver- ter	RS485 / USB converter	RS422 / USB converter (e.g. IF2001/USB)	IF2004/USB			IF2008/ ETH		RS232 / Ethernet converter (e.g. Lantronix X-Port)	RS422 / Ethernet converter (e.g. Lantronix EDS4100)
Hardware	External adapter	RS232	RS485	RS422	USB	RS422	RS422	Ethernet	RS232	RS422		
	Sensor	optoNCDT ILR (ILR118x, ILR1191), optoNCDT (ILD1401, ILD1402), confocalDT (IFD2401, IFD2431), optoCONTROL (ODC1202, ODC1220, ODC2500, ODC2600)	MEBus sensors, capaNCDT (DT6120)	optoNCDT ILR (ILR110x_115x, ILR118x, ILR1191), optoNCDT (ILD1302, ILD1320, ILD1402, ILD1420, ILD1700, ILD1750, ILD1900, ILD2200, ILD2220, ILD2300), confocalDT (IFD2401, IFD2431, IFD2421, IFD2422, IFD2445, IFD2451, IFD2461, IFD2471), optoCONTROL (ODC2500, ODC2520, ODC2600), colorCONTROL (ACS7000), CSP2008, C-Box	confocalDT (IFD2401, IFD2431), C-Box	optoNCDT (ILD1302, ILD1320, ILD1402, ILD1420, ILD1700, ILD1750, ILD1900, ILD2200, ILD2220, ILD2300), confocalDT (IFD2421, IFD2422, IFD2445, IFD2451, IFD2461, IFD2471) optoCONTROL (ODC2500, ODC2520, ODC2600), colorCONTROL (ACS7000), CSP2008, C-Box	same sensors as at IF2004/USB		confocalNCDT (IFD2421, IFD2422, IFD2445, IFD2451, IFD2461, IFD2471), optoNCDT (ILD2300), eddyNCDT (DT306x, DT307x, DT3100), capaNCDT (DT6100, DT6200, DT6500, DT6530), combiSENSOR (KSS6380, KSS64xx), optoCONTROL (ODC2520), colorCONTROL (ACS7000), CSP2008, Eth_IF1032, C-Box, thicknessSENSOR	same sensors as at native RS232 interface	same sensors as at IF2004/ USB	

4. System requirements

- MEDAQLib works at Windows NT, 2000, XP, Vista, Windows7, 8, 10
- RS232 and TCP/IP from Windows NT
- IF2001_USB and IF2004_USB from Windows 2000
- USB (native over WinUSB) and IF2008 from Windows XP
- RS232, IF2001_USB, IF2004_USB, USB (native over WinUSB), IF2008 and TCP/IP for 32 Bit and 64 Bit
- IF2004 for 32 Bit only
- other converters depending on driver (supplied by manufacturer)

5. Internal Structure of MEDAQLib

- Application interface
 - Equal for all sensors and interfaces
- Sensor layer
 - Knows the data protocol and converts binary data into measured values
 - Knows the communication protocol, creates sensors commands and interprets the sensor answer
- Ring buffer (between the layers)
 - Stores binary data and sensor answer coming from interface layer
 - Transfers it to the sensor layer
- Interface layer
 - Communicates with the underlying driver
 - Transmits data from the sensor layer to the sensor, receives data from the sensor and stores it in ring buffer

6. Basic structure of an application

- Create a sensor instance (an own instance for each sensor)
- Set the interface parameters (e.g. “RS232“, “IF2008“ oder “TCP/IP“)
- Open the interface
- Query sensor settings
- If necessary parameterize the sensor (always set command and each parameter using an own function call)
- Continuous reading of sensor values (either complete data blocks or polling latest value for controlling)
- Close the interface
- Release the sensor instance

Each function returns an error value (usually ERR_NOERROR).

If there is an error it must be read.

7. Example program

Example how to open a sensor ILD1402 over RS232 and sending commands:

```
// Creating the instance
DWORD instance= CreateSensorInstance (SENSOR_ILD1402);

// Setting up interface parameter and opening the interface
ERR_CODE err= SetParameterString (instance, "IP_Interface", "RS232");
err= SetParameterString (instance, "IP_Port", "COM1");
err= OpenSensor (instance);

// Receiving sensor settings and getting sensor measurement range
err= SetParameterString (instance, "S_Command", "Get_Settings");
err= SensorCommand (instance);
double range;
err= GetParameterDouble (instance, "SA_Range", &range);

// Set the sampling rate
err= SetParameterString (instance, "S_Command", "Set_Speed");
err= SetParameterInt (instance, "SP_Speed", 1); // 1 means 1.0 kHz
err= SensorCommand (instance);
```

7. Example program

Example for getting number of available values:

```
int avail;  
err= DataAvail (instance, &avail);  
// avail contains now the number of available values.
```

Example for reading continuous data:

```
const int blockSize= 1000;  
int avail, rawData[blockSize];  
double scaledData[blockSize];  
err= TransferData (instance, rawData, scaledData, blockSize, &read);  
// read contains now the number of available values.  
// rawData contains the raw values received from sensor.  
// scaledData contains scaled values.
```

Example for polling latest measurement:

```
int rawData;  
double scaledData;  
err= Poll (instance, &rawData, &scaledData, 1/*only one value*/);  
// rawData contains the latest raw value received from sensor.  
// scaledData contains the latest scaled value.
```

7. Example program

Example for closing the interface and releasing sensor instance:

```
// Close the interface
err= CloseSensor (instance);

// Release the instance
err= ReleaseSensorInstance (instance);
```

Example for reading error text:

```
char errText[1024];
GetError (instance, errText, 1024);
```